

Release notes LidWAP Software
(Windows Application- Firmware)

Windows Application

Type	Date (mm/dd/yy)	Details
V305	30-10-09	Released
	30-10-09	Add Functionality: Possibility to autohide the application at startup
V304	16/03/09	Released
	16/03/09	Released version of all improvements, functionalities and bugfixes
V3.03A	04/09/08	Not Released
Improvement	14/08/08	Moved the config file from root directory to application directory so the file will be stored after a cold reboot.
V3.03	23/07/08	Released
	17/07/08	Released version of all improvements, functionalities and bugfixes.
V3.02C	17/07/08	Not Released
Improvement	17/07/08	Improvement: Possibility to add 'wav' sounds for notification (trigger, tag found, no tag found etc.). When sounds present they will play otherwise system sound will be used.
V3.02B	09/06/08	Not Released
Bug fix	09/06/08	Bugfix: after scanning a tag the application quits or an error message came up when quitting the program. (dependant on os)
V3.02A	03/06/08	Not Released
Improvement	03/06/08	Improvement: Pre-,Suffix settings stored in memory
V3.02	08/05/08	Not Released
Bug fix	08/05/08	Bugfix: Pre-,Suffix dit not work as it should be. Made it work.
V3.01B	23/04/08	Not Released (Special Customer Application) --basket tagging project--
Add functionality	23/04/08	Add button to the WT application to delete log file
V3.01A	21/04/08	Not Released (Special Customer Application) --basket tagging project--
Add functionality	21/04/08	Special application added for customer. Application not available in standard release.
V3.01	15/04/08	Released
Bug fix	15/04/08	Timing problem in trigger mode when application was hidden. Some WAP's had the problem that the trigger button has to be pushed twice to scan.
V3.00	11/04/08	Not Released
Add functionality	11/04/08	Added possibility to write transponder codes to writable tags.
Add functionality	11/04/08	Added possibility to download firmware.
Bug fix	11/04/08	Solved all known bugs
V2.04B	28/02/08	Not Released
Bug fix	28/02/08	Changed the HOTKEY from F23 to F22 because the Enter button fires same event as orange/F23. !! Important for configuration the LidWAP !! (Step 3 LidWAP software manual)
V2.04A	18/02/08	Not Released
Add functionality	18/02/08	Add "No Space" option to print ISO code without any spaces.
Improvement	18/02/08	Add tab option to add vertical tab to the code. (as carriage

		return)
V2.04	08/02/08	Released
Improvement	08/02/08	Enable/Disable country checkbox because only country in DEC mode.
Improvement	08/02/08	Changed text when hide button is pushed.
Improvement	08/02/08	Changed text when comport cannot be opened.
V2.03	14/01/08	Released
Bug fix	14/01/08	Added firmware version control because firmware versions older than V200 where not compatible with Windows application.
V2.02A	07/01/08	Not Released
Bug fix	07/01/08	Some user application didn't get back the focus when scanning bitmap was coming up and a tag scanned.
Improvement	07/01/08	Some visualisation aspects are improved.
V2.02	23/11/07	Released
Improvement	23/11/07	Software compatible for Gen2 WorkaboutPRO.
Add functionality	23/11/07	Added check button for carriage return when application is hidden.
V2.01	15/11/07	Released
Improvement/Bug fix	15/11/07	Changed/modified/added SendCommand functionality.
Improvement/Bug fix	15/11/07	Changed/modified/added Switch Reader On and Off (Pin 71).
Improvement	15/11/07	Functionality added: scan button down -> application start scanning scan button release -> application stop scanning
V2.00	07/11/07	Not Released
Improvement	07/11/07	Combined projects for WindowsCE and WindowsMobile.
V1.05	02/11/07	Not Released
Add functionality	02/11/07	Added HDX check button.
V1.04		Released
Bug fix	18/06/07	By wedge of a transponder in e.g. excel menu options became invisible. (solved).
V1.03	12/07/06	Released
Bug fix	12/07/06	Communication went wrong when a tag was read immediately after pushing the scan button.
Improvement	12/07/06	PSK1,2 Flex and trovan where always visible, even when they where not allowed to be read.
V1.02	13/03/06	Released
Minor bug fix	13/03/06	Text by minimize application was not right.
Improvement	13/03/06	Text added when comport cannot be opened ("application already running?").
Improvement	13/03/06	When application is hidden the reader module will be switched off to saving energy.
V1.01	13/03/06	Released
		First real version with Wedge functionality and hardware button.

Firmware

Type	Date (mm/dd/yy)	Details
V300	07/04/08	Released
Add functionality	07/04/08	Added bootloader.
Add functionality	07/04/08	Added possibility to write writeable tags
V203	30/01/07	Released
Bug fix	30/01/07	Made changes in timerset for ISO tags because problems with reading ISO tags when only ISO was selected.
Bug fix	30/01/07	Fault in ISO DEC -> HEX notation solved (where turned)
Bug fix	30/01/07	ISO country code did not work correct (solved)

V202	07/12/07	Released
Improvement	07/12/07	Software compatible for all settings
V201	06/10/07	Released
Bug fix	06/10/07	Fault after reading AVID solved
Improvement	06/10/07	Fecava/AVID more optimised (Timer values)
Bug fix	06/10/07	Fault in triggermode removed
V200	10/09/07	Released
Improvement	10/09/07	First version suitable for new hardware. New hardware uses new processor (PIC18F2321)
V104	19/04/06	Released
Bug fix	16/01/07	Trovan read routine changed to old principle because new one was not 100% reliable.
V103	09/03/06	Released
Bug fix	16/01/07	Init status of Tx line was low, through that the first character by the first transmission was not correct.
V102	16/01/06	Released
Bug fix	16/01/07	Fault by reading PSK tags solved.
Bug fix	16/01/07	Possibility application hang up in NOGUD loop solved.
V101	16/01/06	Released
Improvement	16/01/07	Firmware version had I on the end. Firmware version always without addition.
Improvement	16/01/07	Standard 100 ms wait after reading a tag due to communication with WAP module.
V100	12/01/06	Released
Initial Version		First Version.